




The procedure how to remove ScanWizard 5 by executing Regedit.exe

Please refer to the following procedure to correct this scanner S/W un-installation / installation problem under PC Windows system.

1. Unplug USB / FireWire cable connection from scanner at first.
2. Open to execute " **Regedit** " from **Start** → **Run**, and then delete the registry of **ScanWizard 5** and its OCR engine : **ABBYY FineReader OCR Engine** from **HKEY_LOCAL_MACHINE \ Software \ Microsoft \ Windows \ Current Version \ Uninstall** in Registry Editor as below illustration.




- a. Delete the registry of **ScanWizard 5** from **HKEY_LOCAL_MACHINE \ Software \ Microsoft \ Windows \ Current Version \ Uninstall \ { B08D262E-D902-11D5-9C28-0080C85A0C2D }**



When you select (**B08D262E-D902-11D5-9C28-0080C85A0C2D**) item in " **Uninstall** ", and then there is message (**Display Name**) → (**ScanWizard 5**) show you as above illustration.


- b. Delete the registry of **ABBYY FineReader OCR Engine** from **HKEY_LOCAL_MACHINE \ Software \ Microsoft \ Windows \ Current Version \ Uninstall \ {345C90FB-FA10-11D5-9C2A-0080C85A0C2D}**



When you select (**345C90FB-FA10-11D5-9C2A-0080C85A0C2D**) item in “ **Uninstall** “, and then there is message (**Display Name**) → (**ABBYY FineReader OCR Engine for ScanWizard**) show you as above illustration.


- c. Quit it from **Registry Editor** under PC Windows system.

3. Delete the folder of “ **ScanWizard 5** “ from path **C : \ Program Files \ Microtek \ ScanWizard 5**.
Delete the folder of “ **ScanWiz 5** “ from path **C : \ WINDOWS \ twain_32 \ ScanWiz 5**.



4. Restart your PC Windows system.
5. Install new version of scanner S/W : ScanWizard 5 from S/W CD, or link to Microtek website in Europe at <http://ww3.microtek.com.tw/eu/modules/tinyd0/index.php?id=2> (select OS : **WinXP**, next, select Product : **ScanMaker 4900** (for example), after that, click “ **GO** ”.), and then download and install new version of SW5 there.

If you install new version of SW5 from new S/W CD, please must select **Not install “ ABBYY OCR Engine for Microtek “** during installation of ScanWizard 5. (**This operation is very important.**)





If you install new version of SW5 from new S/W CD, by this way, you must select **Not install “ ABBYY OCR Engine for Microtek “** during installation of ScanWizard 5.

6. Select to install OCR engine from S/W CD manually.

Or link to Microtek website in Europe at

<http://ww3.microtek.com.tw/eu/modules/tinyd0/index.php?id=2>, download and install English OCR engine : **ABBYY FineReader OCR V4.0** there.



7. Restart your PC Windows system again.

8. Make a USB / FireWire cable connection between PC and your Microtek Scanner.